



Our Ref: IS/RMG/LD20/10

16 July 2010

Bursa LINK Users

Via Email

Dear Sir/Madam

BURSA LINK SYSTEM UPDATE

We refer to the above.

Please be informed that Bursa Malaysia Berhad has changed the EDMS3 IP address with immediate effect.

The change of the EDMS3 IP address is only applicable to Client R7 users. There is no requirement for Web Browser users to update EDMS3 IP address unless you are using both options i.e. Client R7 and Web Browser access. Companies using a proxy server or firewall are advised to inform their internal IT Support to enable / change the following IP address:

Server: EDMS3/EDMS/KLSE
Old IP address: 58.26.56.3
New IP address: 121.123.146.68

For detailed steps to change the IP address, please refer to the guidelines as per Appendix I. The guidelines are also available via Bursa LINK Bulletin Board webpage at <http://www.bursamalaysia.com/website/bm/bursalink.html> - Select "Documents" tab and refer to System Update.


Note: Please get your IT Support assistance to perform the changes as to ensure that the IP address is updated correctly.

For further information and inquiries on the above, kindly contact the following persons:-

- (1) Faizatul Adlin Mohd Adnan : 03-20347576
- (2) Sharifah Norzana Syed Jaafar : 03-20347130
- (3) Saw Xiao Fung : 03-20347238
- (4) Suhairy Saharuddin : 03-20347616

Thank you.

Yours faithfully,


INDERJIT SINGH
Head
Listing Division
Regulation

Encl.


Bursa Malaysia Berhad 30632-P

15th Floor, Exchange Square | Tel : 03-2034 7000, 03-2732 4999 (GL)
Bukit Kewangan | Fax : 03-2026 3684
50200 Kuala Lumpur, Malaysia | Website : www.bursamalaysia.com


Steps to change IP addresses for Client R7

A. Change the IP address in Client R7


1) Launch Client R7 and go to File – Mobile – Locations




The following tab will be displayed:




- From left navigation menu, click on “Connections” and double click on the “EDMS3/EDMS/KLSE” to open the document



- Click on “Edit Connection” button to edit the document




- 4) Go to “Advanced” tab and put in the new IP address as **121.123.146.68** into the “Destination Server Address” field. Click on “Save & Close” to save the changes.




B. Change the IP address on host files.

- 1) From Windows Explorer, navigate to the “C:\Windows\system32\drivers\etc” and find the host file as follows:



- 2) Open the host file using Notepad. Change the IP Address for EDMS3 from 58.26.56.3 to 121.123.146.68



```
hosts - Notepad
File Edit Format View Help
# Copyright (c) 1993-1999 Microsoft Corp.
#
# This is a sample HOSTS file used by Microsoft TCP/IP for Windows.
#
# This file contains the mappings of IP addresses to host names. Each
# entry should be kept on an individual line. The IP address should
# be placed in the first column followed by the corresponding host name.
# The IP address and the host name should be separated by at least one
# space.
#
# Additionally, comments (such as these) may be inserted on individual
# lines or following the machine name denoted by a '#' symbol.
#
# For example:
#       102.54.94.97   rhino.acme.com   # source server
#       38.25.63.10   x.acme.com       # x client host

127.0.0.1       localhost
211.25.178.35   edms1
211.25.178.36   edms2
121.123.146.68 edms3
```

- 3) Go to File – Save, to save the changes.